

**MPLAB 8 Appendix**  
*MPLAB<sup>®</sup> 8 IDE Quick Reference Guide*



**Table of Contents**

**1. Managing Projects**

How to open a project..... B-3

How to save a file or project ..... B-4

How to close a project..... B-4

**2. Building Projects**

How to build a project for production (stand-alone) ..... B-5

How to build a project for debugging..... B-5

**3. Debugging Projects**

How to set or change the debugger ..... B-6

How to control program execution when debugging ..... B-6

How to set and clear breakpoints ..... B-7

How to display and use Watches ..... B-8

# MPLAB 8 Appendix

---

This appendix is intended to be a supplement to lab manuals supplied with a Microchip Technical Training class. Although it may be useful on its own, it is not intended to provide complete instructions for using all aspects of the MPLAB X Integrated Development Environment. For more detailed information on the use of MPLAB X IDE, please consult one of the following Microchip Technical Training classes (for additional details, see <http://www.microchip.com/RTC>):

TLS0101—Getting Started with MPLAB X IDE

TLS0999—Transitioning to MPLAB X IDE for users of MPLAB IDE version 8

Or consult the Microchip Developer's Help Center at [http://microchip.wikidot.com/mplab:\\_start](http://microchip.wikidot.com/mplab:_start)

---

Information contained in this publication regarding device applications and the like is provided only for your convenience and may be superseded by updates. It is your responsibility to ensure that your application meets with your specifications. MICROCHIP MAKES NO REPRESENTATIONS OR WARRANTIES OF ANY KIND HETHER EXPRESS OR IMPLIED, WRITTEN OR ORAL, STATUTORY OR OTHERWISE, RELATED TO THE INFORMATION, INCLUDING BUT NOT LIMITED TO ITS CONDITION, QUALITY, PERFORMANCE, MERCHANTABILITY OR FITNESS FOR PURPOSE. Microchip disclaims all liability arising from this information and its use. Use of Microchip devices in life support and/or safety applications is entirely at the buyer's risk, and the buyer agrees to defend, indemnify and hold harmless Microchip from any and all damages, claims, suits, or expenses resulting from such use. No licenses are conveyed, implicitly or otherwise, under any Microchip intellectual property rights.

## Trademarks

The Microchip name and logo, the Microchip logo, dsPIC, KEELOQ, KEELOQ logo, MPLAB, PIC, PICmicro, PICSTART, PIC32 logo, rfPIC and UNI/O are registered trademarks of Microchip Technology Incorporated in the U.S.A. and other countries.

FilterLab, Hampshire, HI-TECH C, Linear Active Thermistor, MXDEV, MXLAB, SEEVAL and The Embedded Control Solutions Company are registered trademarks of Microchip Technology Incorporated in the U.S.A.

Analog-for-the-Digital Age, Application Maestro, CodeGuard, dsPICDEM, dsPICDEM.net, dsPICworks, dsSPEAK, ECAN, ECONOMONITOR, FanSense, HI-TIDE, In-Circuit Serial Programming, ICSP, Mindi, MiWi, MPASM, MPLAB Certified logo, MPLIB, MPLINK, mTouch, Omniscent Code Generation, PICC, PICC-18, PICDEM, PICDEM.net, PICkit, PICtail, REAL ICE, fLAB, Select Mode, Total Endurance, TSHARC, UniWinDriver, WiperLock and ZENA are trademarks of Microchip Technology Incorporated in the U.S.A. and other countries.

SQTP is a service mark of Microchip Technology Incorporated in the U.S.A.

All other trademarks mentioned herein are property of their respective companies.

© 2011, Microchip Technology Incorporated

## 1. Managing Projects



### Section 1.1

## How to open a project

There are two ways to open a project:

### Method 1:

Navigate to the project's directory and open the "Workspace" (\*.mcw) file by double clicking on it. This will open the workspace associated with the project.

The Workspace file saves everything the Project file (\*.mcp) saves and more. It will save the window position and sizes and watch window contents and settings.

(C:\MTT\classcode\Labx.mcw)

### Information


In most Microchip Technical Training classes, projects are stored in the following directory:

**C:\MTT\classcode**

where *classcode* is specified in the presentation or lab manual.

### Method 2:

- 1** Start MPLAB® 8
- 2** Click on **File ► Open Workspace**
- 3** Navigate to the project's directory and open the "Workspace" (\*.mcw) file.



# MPLAB 8 Appendix



## Section 1.2

### How to save a file or project


#### Method 1:

Click on **File** ► **Save Workspace**



#### Method 2:


Click on the **Save Workspace** icon at the top of the MPLAB<sup>®</sup> IDE



## Section 1.3

### How to close a project

Click on **File** ► **Close Workspace**



## 2. Building Projects



### Section 2.1

## How to build a project for production (stand-alone)

- 1** If you are building a project to run stand-alone (without a debugger) select the “Release” drop down option at the of the MPLAB® IDE.



**2 Method 1:**

If you are building an assembly project or using a Microchip C compiler, click on the “Build All” icon at the top of the MPLAB® IDE



**Build All**

**Method 2:**

If you are using Microchip’s HI-TECH C compiler, click on the “Build with Compiler” icon at the top of the MPLAB® IDE



**Build with Compiler**

**Method 3:**

If you have a large project (many large source files) and made a change in just one source file you can save time by “Making” the project instead of “Building”. “Making” will recompile just the source files that have been changed since the last build. Click on one of these icons at the top of the MPLAB® IDE



**Make**



**Rebuild with Compiler**



### Section 2.2

## How to build a project for debugging

- 1** If you are building a project to use with a debugger (i.e. MPLAB® ICD3, MPLAB® SIM Simulator or Proteus Simulator) select the “Debug” drop down option at the of the MPLAB® IDE.



**2 Method 1:**

If you are building an assembly project or using a Microchip C compiler, click on the “Build All” icon at the top of the MPLAB® IDE



**Build All**

**Method 2:**

If you are using Microchip’s HI-TECH C compiler, click on the “Build with Compiler” icon at the top of the MPLAB® IDE



**Build with Compiler**

**Method 3:**

If you have a large project (many large source files) and made a change in just one source file you can save time by “Making” the project instead of “Building”. “Making” will recompile just the source files that have been changed since the last build. Click on one of these icons at the top of the MPLAB® IDE



**Make**



**Rebuild with Compiler**

# MPLAB 8 Appendix


## 3. Debugging Projects



### Section 3.1

## How to set or change the debugger

Click on **Debugger** ► **Select Tool** and choose your debugger from the list.



### Section 3.2

## How to control program execution when debugging

### Debug Toolbar Buttons



**Run (F9)** the program



**Pause (F5)**



**Step into** or single step (F7) - Execute the next instruction



**Step Over (F8)** - Execute each line without stepping into functions (functions are executed without stepping through each line)



**Step Out** - Execute all instructions in the current function or sub routine then stop program execution



**Reset (F6)**



### Information


When you hover the mouse pointer over a toolbar button a tool tip will be displayed explaining the function of the button.



## Section 3.3

### How to set and clear breakpoints

Standard line breakpoints may be set or cleared by clicking on the line number in the glyph margin.



More advanced breakpoint features may be accessed by opening the breakpoints window. From the main menu select **Debugger ► Breakpoints**.


# MPLAB 8 Appendix




## Section 3.4

### How to display and use Watches

- 1 To view the contents of a data memory location click on **View** ► **Watch** to open a watch window.



- 2 To add a variable to the watch window highlight the variable you want to watch in the editor
- 3 Then drag-and-drop it into the watch window





This page intentionally blank